Commandline

Update Address	Type	Name	Example
/Mx/commandLine/0001/color	color	Command Line Status	white
/Mx/commandLine/0001/text	string	Command Line Status	FREE
/Mx/commandLine/0001/text/color	color	Command Line Status	red

/Mx/commandLine/0002/color	color	Command Line Command	White
/Mx/commandLine/0002/text	string	Command Line Command	<command/>
/Mx/commandLine/0002/text/color	color	Command Line Command	black

Playback

For playback execute messages a license is required.

Update Address	Туре	Name	Example
/Mx/button/4201/led	int	PFA 1	0 or 1
/Mx/button/4201/led/color	color	PFA 1	blue or red
/Mx/button/4201/led/blink	int	PFA 1	0 or 1
/Mx/button/4202/led	int	PFB 1	0 or 1
/Mx/button/4202/led/color	color	PFB 1	blue or red
/Mx/button/4202/led/blink	int	PFB 1	0 or 1
/Mx/fader/4203	float	LEVEL PLAYBACK 1	0 to 255
/Mx/fader/4203/color	color	LEVEL PLAYBACK 1	gray
/Mx/button/4204/text	string	PFC 1	<name></name>
/Mx/button/4204/color	color	PFC 1	gray
/Mx/button/4204/text/color	color	PFC 1	gray
/Mx/button/4205/led	int	PFD 1	0 or 1
/Mx/button/4205/led/color	color	PFD 1	green
Execute Address	Type	Name	Example
/Mx/button/4201	up/down	PFA 1	0 or 1
/Mx/button/4202	up/down	PFB 1	0 or 1
/Mx/fader/4203	float	LEVEL PLAYBACK 1	0 to 255
/Mx/button/4204	up/down	PFC 1	0 or 1
/Mx/button/4205	up/down	PFD 1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4211/led	int	PFA 2	0 or 1
/Mx/button/4211/led/color	color	PFA 2	blue or red
/Mx/button/4211/led/blink	int	PFA 2	0 or 1
/Mx/button/4212/led	int	PFB 2	0 or 1
/Mx/button/4212/led/color	color	PFB 2	blue or red
/Mx/button/4212/led/blink	int	PFB 2	0 or 1
/Mx/fader/4213	float	LEVEL PLAYBACK 2	0 to 255
/Mx/fader/4213/color	color	LEVEL PLAYBACK 2	gray
/Mx/button/4214/text	string	PFC 2	<name></name>

/Mx/button/4214/color	color	PFC 2	gray
/Mx/button/4214/text/color	color	PFC 2	gray
/Mx/button/4215/led	int	PFD 2	0 or 1
/Mx/button/4215/led/color	color	PFD 2	green
Execute Address	Туре	Name	Example
/Mx/button/4211	up/down	PFA 2	0 or 1
/Mx/button/4212	up/down	PFB 2	0 or 1
/Mx/fader/4213	float	LEVEL PLAYBACK 2	0 to 255
/Mx/button/4214	up/down	PFC 2	0 or 1
/Mx/button/4215	up/down	PFD 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4221/led	int	PFA 3	0 or 1
/Mx/button/4221/led/color	color	PFA 3	blue or red
/Mx/button/4221/led/blink	int	PFA 3	0 or 1
/Mx/button/4222/led	int	PFB 3	0 or 1
/Mx/button/4222/led/color	color	PFB 3	blue or red
/Mx/button/4222/led/blink	int	PFB 3	0 or 1
/Mx/fader/4223	float	LEVEL PLAYBACK 3	0 to 255
/Mx/fader/4223/color	color	LEVEL PLAYBACK 3	gray
/Mx/button/4224/text	string	PFC 3	<name></name>
/Mx/button/4224/color	color	PFC 3	gray
/Mx/button/4224/text/color	color	PFC 3	gray
/Mx/button/4225/led	int	PFD 3	0 or 1
/Mx/button/4225/led/color	color	PFD 3	green
Execute Address	Type	Namespace	Example
/Mx/button/4221	up/down	PFA 3	0 or 1
/Mx/button/4222	up/down	PFB 3	0 or 1
/Mx/fader/4223	float	LEVEL PLAYBACK 3	0 to 255
/Mx/button/4224	up/down	PFC 3	0 or 1
/Mx/button/4225	up/down	PFD 3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4231/led	int	PFA 4	0 or 1
/Mx/button/4231/led/color	color	PFA 4	blue or red
/Mx/button/4231/led/blink	int	PFA 4	0 or 1
/Mx/button/4232/led	int	PFB 4	0 or 1
/Mx/button/4232/led/color	color	PFB 4	blue or red
/Mx/button/4232/led/blink	int	PFB 4	0 or 1
/Mx/fader/4233	float	LEVEL PLAYBACK 4	0 to 255
/Mx/fader/4233/color	color	LEVEL PLAYBACK 4	gray
/Mx/button/4234/text	string	PFC 4	<name></name>
/Mx/button/4234/color	color	PFC 4	gray
/Mx/button/4234/text/color	color	PFC 4	gray
/Mx/button/4235/led	int	PFD 4	0 or 1
/Mx/button/4235/led/color	color	PFD 4	green
Execute Address	Туре	Namespace	Example
/Mx/button/4231	up/down	PFA 4	0 or 1

/Mx/button/4232	up/down	PFB 4	0 or 1
/Mx/fader/4233	float	LEVEL PLAYBACK 4	0 to 255
/Mx/button/4234	up/down	PFC 4	0 or 1
/Mx/button/4235	up/down	PFD 4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4241/led	int	PFA 5	0 or 1
/Mx/button/4241/led/color	color	PFA 5	blue or red
/Mx/button/4241/led/blink	int	PFA 5	0 or 1
/Mx/button/4242/led	int	PFB 5	0 or 1
/Mx/button/4242/led/color	color	PFB 5	blue or red
/Mx/button/4242/led/blink	int	PFB 5	0 or 1
/Mx/fader/4243	float	LEVEL PLAYBACK 5	0 to 255
/Mx/fader/4243/color	color	LEVEL PLAYBACK 5	gray
/Mx/button/4244/text	string	PFC 5	<name></name>
/Mx/button/4244/color	color	PFC 5	gray
/Mx/button/4244/text/color	color	PFC 5	gray
/Mx/button/4245/led	int	PFD 5	0 or 1
/Mx/button/4245/led/color	color	PFD 5	green
Execute Address	Туре	Name	Example
/Mx/button/4241	up/down	PFA 5	0 or 1
/Mx/button/4242	up/down	PFB 5	0 or 1
/Mx/fader/4243	float	LEVEL PLAYBACK 5	0 to 255
/Mx/button/4244	up/down	PFC 5	0 or 1
/Mx/button/4245	up/down	PFD 5	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4251/led	int	PFA 6	0 or 1
/Mx/button/4251/led/color	color	PFA 6	blue or red
/Mx/button/4251/led/blink	int	PFA 6	0 or 1
/Mx/button/4252/led	int	PFB 6	0 or 1
/Mx/button/4252/led/color	color	PFB 6	blue or red
/Mx/button/4252/led/blink	int	PFB 6	0 or 1
/Mx/fader/4253	float	LEVEL PLAYBACK 6	0 to 255
/Mx/fader/4253/color	color	LEVEL PLAYBACK 6	gray
/Mx/button/4254/text	string	PFC 6	<name></name>
/Mx/button/4254/color	color	PFC 6	gray
/Mx/button/4254/text/color	color	PFC 6	gray
/Mx/button/4255/led	int	PFD 6	0 or 1
/Mx/button/4255/led/color	color	PFD 6	green
Execute Address	Туре	Name	Example
/Mx/button/4251	up/down	PFA 6	0 or 1
/Mx/button/4252	up/down	PFB 6	0 or 1
/Mx/fader/4253	float	LEVEL PLAYBACK 6	0 to 255
/Mx/button/4254	up/down	PFC 6	0 or 1
/Mx/button/4255	up/down	PFD 6	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4261/led	int	PFA 7	0 or 1
/Mx/button/4261/led/color	color	PFA 7	blue or red
/Mx/button/4261/led/blink	int	PFA 7	0 or 1
/Mx/button/4262/led	int	PFB 7	0 or 1
/Mx/button/4262/led/color	color	PFB 7	blue or red
/Mx/button/4262/led/blink	int	PFB 7	0 or 1
/Mx/fader/4263	float	LEVEL PLAYBACK 7	0 to 255
/Mx/fader/4263/color	color	LEVEL PLAYBACK 7	gray
/Mx/button/4264/text	string	PFC 7	<name></name>
/Mx/button/4264/color	color	PFC 7	gray
/Mx/button/4264/text/color	color	PFC 7	gray
/Mx/button/4265/led	int	PFD 7	0 or 1
/Mx/button/4265/led/color	color	PFD 7	green
Execute Address	Туре	Name	Example
/Mx/button/4261	up/down	PFA 7	0 or 1
/Mx/button/4262	up/down	PFB 7	0 or 1
/Mx/fader/4263	float	LEVEL PLAYBACK 7	0 to 255
/Mx/button/4264	up/down	PFC 7	0 or 1
/Mx/button/4265	up/down	PFD 7	0 or 1

Update Address	Type	Name	Example
/Mx/button/4271/led	int	PFA 8	0 or 1
/Mx/button/4271/led/color	color	PFA 8	blue or red
/Mx/button/4271/led/blink	int	PFA 8	0 or 1
/Mx/button/4272/led	int	PFB 8	0 or 1
/Mx/button/4272/led/color	color	PFB 8	blue or red
/Mx/button/4272/led/blink	int	PFB 8	0 or 1
/Mx/fader/4273	float	LEVEL PLAYBACK 8	0 to 255
/Mx/fader/4273/color	color	LEVEL PLAYBACK 8	gray
/Mx/button/4274/text	string	PFC 8	<name></name>
/Mx/button/4274/color	color	PFC 8	gray
/Mx/button/4274/text/color	color	PFC 8	gray
/Mx/button/4275/led	int	PFD 8	0 or 1
/Mx/button/4275/led/color	color	PFD 8	green
Execute Address	Туре	Name	Example
/Mx/button/4271	up/down	PFA 8	0 or 1
/Mx/button/4272	up/down	PFB 8	0 or 1
/Mx/fader/4273	float	LEVEL PLAYBACK 8	0 to 255
/Mx/button/4274	up/down	PFC 8	0 or 1
/Mx/button/4275	up/down	PFD 8	0 or 1

Update Address	Type	Name	Example
/Mx/button/4281/led	int	PFA 9	0 or 1
/Mx/button/4281/led/color	color	PFA 9	blue or red
/Mx/button/4281/led/blink	int	PFA 9	0 or 1
/Mx/button/4282/led	int	PFB 9	0 or 1
/Mx/button/4282/led/color	color	PFB 9	blue or red

/Mx/button/4282/led/blink	int	PFB 9	0 or 1
/Mx/fader/4283	float	LEVEL PLAYBACK 9	0 to 255
/Mx/fader/4283/color	color	LEVEL PLAYBACK 9	gray
/Mx/button/4284/text	string	PFC 9	<name></name>
/Mx/button/4284/color	color	PFC 9	gray
/Mx/button/4284/text/color	color	PFC 9	gray
/Mx/button/4285/led	int	PFD 9	0 or 1
/Mx/button/4285/led/color	color	PFD 9	green
Execute Address	Type	Name	Example
/Mx/button/4281	up/down	PFA 9	0 or 1
/Mx/button/4282	up/down	PFB 9	0 or 1
/Mx/fader/4283	float	LEVEL PLAYBACK 9	0 to 255
/Mx/button/4284	up/down	PFC 9	0 or 1
/Mx/button/4285	up/down	PFD 9	0 or 1

Update Address	Type	Name	Example
/Mx/button/4291/led	int	PFA 10	0 or 1
/Mx/button/4291/led/color	color	PFA 10	blue or red
/Mx/button/4291/led/blink	int	PFA 10	0 or 1
/Mx/button/4292/led	int	PFB 10	0 or 1
/Mx/button/4292/led/color	color	PFB 10	blue or red
/Mx/button/4292/led/blink	int	PFB 10	0 or 1
/Mx/fader/4293	float	LEVEL PLAYBACK 10	0 to 255
/Mx/fader/4293/color	color	LEVEL PLAYBACK 10	gray
/Mx/button/4294/text	string	PFC 10	<name></name>
/Mx/button/4294/color	color	PFC 10	gray
/Mx/button/4294/text/color	color	PFC 10	gray
/Mx/button/4295/led	int	PFD 10	0 or 1
/Mx/button/4295/led/color	color	PFD 10	green
Execute Address	Type	Name	Example
/Mx/button/4291	up/down	PFA 10	0 or 1
/Mx/button/4292	up/down	PFB 10	0 or 1
/Mx/fader/4293	float	LEVEL PLAYBACK 10	0 to 255
/Mx/button/4294	up/down	PFC 10	0 or 1
/Mx/button/4295	up/down	PFD 10	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4601/led	int	PFA 11	0 or 1
/Mx/button/4601/led/color	color	PFA 11	blue or red
/Mx/button/4601/led/blink	int	PFA 11	0 or 1
/Mx/button/4602/led	int	PFB 11	0 or 1
/Mx/button/4602/led/color	color	PFB 11	blue or red
/Mx/button/4602/led/blink	int	PFB 11	0 or 1
/Mx/fader/4603	float	LEVEL PLAYBACK 11	0 to 255
/Mx/fader/4603/color	color	LEVEL PLAYBACK 11	gray
/Mx/button/4604/text	string	PFC 11	<name></name>
/Mx/button/4604/color	color	PFC 11	gray
/Mx/button/4604/text/color	color	PFC 11	gray

/Mx/button/4605/led	int	PFD 11	0 or 1
/Mx/button/4605/led/color	color	PFD 11	green
Execute Address	Туре	Name	Example
/Mx/button/4601	up/down	PFA 11	0 or 1
/Mx/button/4602	up/down	PFB 11	0 or 1
/Mx/fader/4603	float	LEVEL PLAYBACK 11	0 to 255
/Mx/button/4604	up/down	PFC 11	0 or 1
/Mx/button/4605	up/down	PFD 11	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4611/led	int	PFA 12	0 or 1
/Mx/button/4611/led/color	color	PFA 12	blue or red
/Mx/button/4611/led/blink	int	PFA 12	0 or 1
/Mx/button/4612/led	int	PFB 12	0 or 1
/Mx/button/4612/led/color	color	PFB 12	blue or red
/Mx/button/4612/led/blink	int	PFB 12	0 or 1
/Mx/fader/4613	float	LEVEL PLAYBACK 12	0 to 255
/Mx/fader/4613/color	color	LEVEL PLAYBACK 12	gray
/Mx/button/4614/text	string	PFC 12	<name></name>
/Mx/button/4614/color	color	PFC 12	gray
/Mx/button/4614/text/color	color	PFC 12	gray
/Mx/button/4615/led	int	PFD 12	0 or 1
/Mx/button/4615/led/color	color	PFD 12	green
Execute Address	Туре	Name	Example
/Mx/button/4611	up/down	PFA 12	0 or 1
/Mx/button/4612	up/down	PFB 12	0 or 1
/Mx/fader/4613	float	LEVEL PLAYBACK 12	0 to 255
/Mx/button/4614	up/down	PFC 12	0 or 1
/Mx/button/4615	up/down	PFD 12	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4621/led	int	PFA 13	0 or 1
/Mx/button/4621/led/color	color	PFA 13	blue or red
/Mx/button/4621/led/blink	int	PFA 13	0 or 1
/Mx/button/4622/led	int	PFB 13	0 or 1
/Mx/button/4622/led/color	color	PFB 13	blue or red
/Mx/button/4622/led/blink	int	PFB 13	0 or 1
/Mx/fader/4623	float	LEVEL PLAYBACK 13	0 to 255
/Mx/fader/4623/color	color	LEVEL PLAYBACK 13	gray
/Mx/button/4624/text	string	PFC 13	<name></name>
/Mx/button/4624/color	color	PFC 13	gray
/Mx/button/4624/text/color	color	PFC 13	gray
/Mx/button/4625/led	int	PFD 13	0 or 1
/Mx/button/4625/led/color	color	PFD 13	green
Execute Address	Туре	Name	Example
/Mx/button/4621	up/down	PFA 13	0 or 1
/Mx/button/4622	up/down	PFB 13	0 or 1
/Mx/fader/4623	float	LEVEL PLAYBACK 13	0 to 255

/Mx/button/4624	up/down	PFC 13	0 or 1
/Mx/button/4625	up/down	PFD 13	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4631/led	int	PFA 14	0 or 1
/Mx/button/4631/led/color	color	PFA 14	blue or red
/Mx/button/4631/led/blink	int	PFA 14	0 or 1
/Mx/button/4632/led	int	PFB 14	0 or 1
/Mx/button/4632/led/color	color	PFB 14	blue or red
/Mx/button/4632/led/blink	int	PFB 14	0 or 1
/Mx/fader/4633	float	LEVEL PLAYBACK 14	0 to 255
/Mx/fader/4633/color	color	LEVEL PLAYBACK 14	gray
/Mx/button/4634/text	string	PFC 14	<name></name>
/Mx/button/4634/color	color	PFC 14	gray
/Mx/button/4634/text/color	color	PFC 14	gray
/Mx/button/4635/led	int	PFD 14	0 or 1
/Mx/button/4635/led/color	color	PFD 14	green
Execute Address	Type	Name	Example
/Mx/button/4631	up/down	PFA 14	0 or 1
/Mx/button/4632	up/down	PFB 14	0 or 1
/Mx/fader/4633	float	LEVEL PLAYBACK 14	0 to 255
/Mx/button/4634	up/down	PFC 14	0 or 1
/Mx/button/4635	up/down	PFD 14	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4641/led	int	PFA 15	0 or 1
/Mx/button/4641/led/color	color	PFA 15	blue or red
/Mx/button/4641/led/blink	int	PFA 15	0 or 1
/Mx/button/4642/led	int	PFB 15	0 or 1
/Mx/button/4642/led/color	color	PFB 15	blue or red
/Mx/button/4642/led/blink	int	PFB 15	0 or 1
/Mx/fader/4643	float	LEVEL PLAYBACK 15	0 to 255
/Mx/fader/4643/color	color	LEVEL PLAYBACK 15	gray
/Mx/button/4644/text	string	PFC 15	<name></name>
/Mx/button/4644/color	color	PFC 15	gray
/Mx/button/4644/text/color	color	PFC 15	gray
/Mx/button/4645/led	int	PFD 15	0 or 1
/Mx/button/4645/led/color	color	PFD 15	green
Execute Address	Туре	Name	Example
/Mx/button/4641	up/down	PFA 15	0 or 1
/Mx/button/4642	up/down	PFB 15	0 or 1
/Mx/fader/4643	float	LEVEL PLAYBACK 15	0 to 255
/Mx/button/4644	up/down	PFC 15	0 or 1
/Mx/button/4645	up/down	PFD 15	0 or 1

Update Address	Type	Name	Example
/Mx/button/4651/led	int	PFA 16	0 or 1

/Mx/button/4651/led/color	color	PFA 16	blue or red
/Mx/button/4651/led/blink	int	PFA 16	0 or 1
/Mx/button/4652/led	int	PFB 16	0 or 1
/Mx/button/4652/led/color	color	PFB 16	blue or red
/Mx/button/4652/led/blink	int	PFB 16	0 or 1
/Mx/fader/4653	float	LEVEL PLAYBACK 16	0 to 255
/Mx/fader/4653/color	color	LEVEL PLAYBACK 16	gray
/Mx/button/4654/text	string	PFC 16	<name></name>
/Mx/button/4654/color	color	PFC 16	gray
/Mx/button/4654/text/color	color	PFC 16	gray
/Mx/button/4655/led	int	PFD 16	0 or 1
/Mx/button/4655/led/color	color	PFD 16	green
Execute Address	Type	Name	Example
/Mx/button/4651	up/down	PFA 16	0 or 1
/Mx/button/4652	up/down	PFB 16	0 or 1
/Mx/fader/4653	float	LEVEL PLAYBACK 16	0 to 255
/Mx/button/4654	up/down	PFC 16	0 or 1
/Mx/button/4655	up/down	PFD 16	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4661/led	int	PFA 17	0 or 1
/Mx/button/4661/led/color	color	PFA 17	blue or red
/Mx/button/4661/led/blink	int	PFA 17	0 or 1
/Mx/button/4662/led	int	PFB 17	0 or 1
/Mx/button/4662/led/color	color	PFB 17	blue or red
/Mx/button/4662/led/blink	int	PFB 17	0 or 1
/Mx/fader/4663	float	LEVEL PLAYBACK 17	0 to 255
/Mx/fader/4663/color	color	LEVEL PLAYBACK 17	gray
/Mx/button/4664/text	string	PFC 17	<name></name>
/Mx/button/4664/color	color	PFC 17	gray
/Mx/button/4664/text/color	color	PFC 17	gray
/Mx/button/4665/led	int	PFD 17	0 or 1
/Mx/button/4665/led/color	color	PFD 17	green
Execute Address	Туре	Name	Example
/Mx/button/4661	up/down	PFA 17	0 or 1
/Mx/button/4662	up/down	PFB 17	0 or 1
/Mx/fader/4663	float	LEVEL PLAYBACK 17	0 to 255
/Mx/button/4664	up/down	PFC 17	0 or 1
/Mx/button/4665	up/down	PFD 17	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4671/led	int	PFA 18	0 or 1
/Mx/button/4671/led/color	color	PFA 18	blue or red
/Mx/button/4671/led/blink	int	PFA 18	0 or 1
/Mx/button/4672/led	int	PFB 18	0 or 1
/Mx/button/4672/led/color	color	PFB 18	blue or red
/Mx/button/4672/led/blink	int	PFB 18	0 or 1
/Mx/fader/4673	float	LEVEL PLAYBACK 18	0 to 255

/Mx/fader/4673/color	color	LEVEL PLAYBACK 18	gray
/Mx/button/4674/text	string	PFC 18	<name></name>
/Mx/button/4674/color	color	PFC 18	gray
/Mx/button/4674/text/color	color	PFC 18	gray
/Mx/button/4675/led	int	PFD 18	0 or 1
/Mx/button/4675/led/color	color	PFD 18	green
Execute Address	Туре	Name	Example
/Mx/button/4671	up/down	PFA 18	0 or 1
/Mx/button/4672	up/down	PFB 18	0 or 1
/Mx/fader/4673	float	LEVEL PLAYBACK 18	0 to 255
/Mx/button/4674	up/down	PFC 18	0 or 1
/Mx/button/4675	up/down	PFD 18	0 or 1

Update Address	Type	Name	Example
/Mx/button/4681/led	int	PFA 19	0 or 1
/Mx/button/4681/led/color	color	PFA 19	blue or red
/Mx/button/4681/led/blink	int	PFA 19	0 or 1
/Mx/button/4682/led	int	PFB 19	0 or 1
/Mx/button/4682/led/color	color	PFB 19	blue or red
/Mx/button/4682/led/blink	int	PFB 19	0 or 1
/Mx/fader/4683	float	LEVEL PLAYBACK 19	0 to 255
/Mx/fader/4683/color	color	LEVEL PLAYBACK 19	gray
/Mx/button/4684/text	string	PFC 19	<name></name>
/Mx/button/4684/color	color	PFC 19	gray
/Mx/button/4684/text/color	color	PFC 19	gray
/Mx/button/4685/led	int	PFD 19	0 or 1
/Mx/button/4685/led/color	color	PFD 19	green
Execute Address	Type	Name	Example
/Mx/button/4681	up/down	PFA 19	0 or 1
/Mx/button/4682	up/down	PFB 19	0 or 1
/Mx/fader/4683	float	LEVEL PLAYBACK 19	0 to 255
/Mx/button/4684	up/down	PFC 19	0 or 1
/Mx/button/4685	up/down	PFD 19	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4691/led	int	PFA 20	0 or 1
/Mx/button/4691/led/color	color	PFA 20	blue or red
/Mx/button/4691/led/blink	int	PFA 20	0 or 1
/Mx/button/4692/led	int	PFB 20	0 or 1
/Mx/button/4692/led/color	color	PFB 20	blue or red
/Mx/button/4692/led/blink	int	PFB 20	0 or 1
/Mx/fader/4693	float	LEVEL PLAYBACK 20	0 to 255
/Mx/fader/4693/color	color	LEVEL PLAYBACK 20	gray
/Mx/button/4694/text	string	PFC 20	<name></name>
/Mx/button/4694/color	color	PFC 20	gray
/Mx/button/4694/text/color	color	PFC 20	gray
/Mx/button/4695/led	int	PFD 20	0 or 1
/Mx/button/4695/led/color	color	PFD 20	green

Execute Address	Туре	Name	Example
/Mx/button/4691	up/down	PFA 20	0 or 1
/Mx/button/4692	up/down	PFB 20	0 or 1
/Mx/fader/4693	float	LEVEL PLAYBACK 20	0 to 255
/Mx/button/4694	up/down	PFC 20	0 or 1
/Mx/button/4695	up/down	PFD 20	0 or 1

Update Address	Type	Name	Example
/Mx/button/5502/led	int	SELECT	0 or 1
/Mx/button/5502/led/color	color	SELECT	blue or red
/Mx/button/5502/led/blink	int	SELECT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5502	up/down	SELECT	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5503/led	int	RELEASE	0 or 1
/Mx/button/5503/led/color	color	RELEASE	blue or red
/Mx/button/5503/led/blink	int	RELEASE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5503	up/down	RELEASE	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5504/led	int	BEAT	0 or 1
/Mx/button/5504/led/color	color	BEAT	blue or red
/Mx/button/5504/led/blink	int	BEAT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5504	up/down	BEAT	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5511/led	int	SNAP	0 or 1
/Mx/button/5511/led/color	color	SNAP	blue or red
/Mx/button/5511/led/blink	int	SNAP	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5511	up/down	SNAP	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5512/led	int	/Back	0 or 1
/Mx/button/5512/led/color	color	/Back	blue or red
/Mx/button/5512/led/blink	int	/Back	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5512	up/down	/Back	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5513/led	int	GO	0 or 1
/Mx/button/5513/led/color	color	GO	blue or red

/Mx/button/5513/led/blink	int	GO	0 or 1
Execute Address	Type	Name	Example
/Mx/button/5513	up/down	GO	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4121/led	int	View	0 or 1
/Mx/button/4121/led/color	color	View	blue or red
/Mx/button/4121/led/blink	int	View	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4121	up/down	View	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4412/led	int	Bank Page Up	0 or 1
/Mx/button/4412/led/color	color	Bank Page Up	blue or red
/Mx/button/4412/led/blink	int	Bank Page Up	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4412	up/down	Bank Page Up	0 or 1

Update Address	Type	Name	Example
/Mx/button/4413/led	int	Bank Page Down	0 or 1
/Mx/button/4413/led/color	color	Bank Page Down	blue or red
/Mx/button/4413/led/blink	int	Bank Page Down	0 or 1
Execute Address	Type	Name	Example
/Mx/button/4413	up/down	Bank Page Down	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4421/text	string	PLAYBACK BANK 1	<name></name>
/Mx/button/4421/color	color	PLAYBACK BANK 1	green
/Mx/button/4421/text/color	color	PLAYBACK BANK 1	gray
Execute Address	Туре	Name	Example
/Mx/button/4421	up/down	PLAYBACK BANK 1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4422/text	string	PLAYBACK BANK 2	<name></name>
/Mx/button/4422/color	color	PLAYBACK BANK 2	green
/Mx/button/4422/text/color	color	PLAYBACK BANK 2	gray
Execute Address	Туре	Name	Example
/Mx/button/4422	up/down	PLAYBACK BANK 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4423/text	string	PLAYBACK BANK 3	<name></name>
/Mx/button/4423/color	color	PLAYBACK BANK 3	green
/Mx/button/4423/text/color	color	PLAYBACK BANK 3	gray
Execute Address	Туре	Name	Example
/Mx/button/4423	up/down	PLAYBACK BANK 3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4424/text	string	PLAYBACK BANK 4	<name></name>
/Mx/button/4424/color	color	PLAYBACK BANK 4	green
/Mx/button/4424/text/color	color	PLAYBACK BANK 4	gray
Execute Address	Туре	Name	Example
/Mx/button/4424	up/down	PLAYBACK BANK 4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4425/text	string	PLAYBACK BANK 5	<name></name>
/Mx/button/4425/color	color	PLAYBACK BANK 5	green
/Mx/button/4425/text/color	color	PLAYBACK BANK 5	gray
Execute Address	Туре	Name	Example
/Mx/button/4425	up/down	PLAYBACK BANK 5	0 or 1

Update Address	Туре	Name	Example
/Mx/label/4401/text	string	PLAYBACK BANK NUMBER	<name></name>
/Mx/label/4401/color	color	PLAYBACK BANK NUMBER	black
/Mx/label/4401/text/color	color	PLAYBACK BANK NUMBER	white

Execute Address	Туре	Name	Example
/Mx/scroll/4110/up	up/down	Bank Scroll Up	0 or 1
/Mx/scroll/4110/down	up/down	Bank Scroll Down	0 or 1

Execute Address	Туре	Name	Example
/Mx/scroll/4111/up	up/down	Bank Page Scroll Up	0 or 1
/Mx/scroll/4111/down	up/down	Bank Page Scroll Down	0 or 1

Execute Address	Type	Name	Example
/Mx/button/4600	up/down	Fader Swap	0 or 1

Playback Pages

For playback page execute messages a license is required. No update messages exist for the playback pages.

Execute Address	Туре	Name	Example
/Mx/playback/page <pageindex>/<buttonindex>/<action></action></buttonindex></pageindex>	up/down	Playback	0 or 1
		Pages	

Syntax: /Mx/playback/page<pageIndex>/<buttonIndex>/<action value>

Page Index: 1 – 100 (one bases index)
Button Index: 0 – 99 (zero bases index)

• Action: (not case sensitive)

Action	String Value
Go	"PLAY" or "GO"
Pause	"PAUSE"
Release	"RELEASE"
Select	"SELECT"
SnapGo	"SNAPGO"
Toggle	"TOGGLE"
Back	"BACK"

Examples:

/Mx/playback/page1/0/go 1 Execute a key down, go action on page 1, button 1
/Mx/playback/page5/9/release 1 Execute a key down, release action on page 5, button 10

Master Faders

Update Address	Type	Name	Example
/Mx/button/2201/led	int	GRAND MASTER FLASH	0 or 1
/Mx/button/2201/led/color	color	GRAND MASTER FLASH	blue or red
/Mx/button/2201/led/blink	int	GRAND MASTER FLASH	0 or 1
Execute Address	Туре	Name	Example
/Mx/fader/2202	float	GRAND MASTER LEVEL	0 to 255

Update Address	Туре	Name	Example
/Mx/button/2211/led	int	FLASH MASTER FLASH	0 or 1
/Mx/button/2211/led/color	color	FLASH MASTER FLASH	blue or red
/Mx/button/2211/led/blink	int	FLASH MASTER FLASH	0 or 1
Execute Address	Туре	Name	Example
/Mx/fader/2212	float	FLASH MASTER LEVEL	0 to 255

Update Address	Туре	Name	Example
/Mx/button/2221/led	int	GROUP MASTER A FLASH	0 or 1
/Mx/button/2221/led/color	color	GROUP MASTER A FLASH	blue or red
/Mx/button/2221/led/blink	int	GROUP MASTER A FLASH	0 or 1
Execute Address	Type	Name	Example
/Mx/fader/2222	float	GROUP MASTER A LEVEL	0 to 255

Update Address	Туре	Name	Example
/Mx/button/2231/led	int	GROUP MASTER B FLASH	0 or 1
/Mx/button/2231/led/color	color	GROUP MASTER B FLASH	blue or red
/Mx/button/2231/led/blink	int	GROUP MASTER B FLASH	0 or 1
Execute Address	Туре	Name	Example
/Mx/fader/2232	float	GROUP MASTER B LEVEL	0 to 255

Screens

Update Address	Туре	Name	Example
/Mx/button/1101/led	int	VIEW 1	0 or 1
/Mx/button/1101/led/color	color	VIEW 1	blue or red
/Mx/button/1101/led/blink	int	VIEW 1	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1101	up/down	VIEW 1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/1102/led	int	VIEW 2	0 or 1
/Mx/button/1102/led/color	color	VIEW 2	blue or red
/Mx/button/1102/led/blink	int	VIEW 2	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1102	up/down	VIEW 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/1103/led	int	VIEW 3	0 or 1
/Mx/button/1103/led/color	color	VIEW 3	blue or red
/Mx/button/1103/led/blink	int	VIEW 3	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1103	up/down	VIEW 3	0 or 1

Update Address	Type	Name	Example
/Mx/button/1104/led	int	VIEW 4	0 or 1
/Mx/button/1104/led/color	color	VIEW 4	blue or red
/Mx/button/1104/led/blink	int	VIEW 4	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1104	up/down	VIEW 4	0 or 1

Update Address	Type	Name	Example
/Mx/button/1105/led	int	VIEW 5	0 or 1
/Mx/button/1105/led/color	color	VIEW 5	blue or red
/Mx/button/1105/led/blink	int	VIEW 5	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1105	up/down	VIEW 5	0 or 1

Update Address	Туре	Name	Example
/Mx/button/1106/led	int	VIEW 6	0 or 1
/Mx/button/1106/led/color	color	VIEW 6	blue or red
/Mx/button/1106/led/blink	int	VIEW 6	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1106	up/down	VIEW 6	0 or 1

Update Address	Туре	Name	Example
/Mx/button/1107/led	int	VIEW 7	0 or 1
/Mx/button/1107/led/color	color	VIEW 7	blue or red
/Mx/button/1107/led/blink	int	VIEW 7	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1107	up/down	VIEW 7	0 or 1

Update Address	Туре	Name	Example
/Mx/button/1108/led	int	VIEW 8	0 or 1
/Mx/button/1108/led/color	color	VIEW 8	blue or red
/Mx/button/1108/led/blink	int	VIEW 8	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/1108	up/down	VIEW 8	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3101/led	int	VIEW 9	0 or 1
/Mx/button/3101/led/color	color	VIEW 9	blue or red
/Mx/button/3101/led/blink	int	VIEW 9	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3101	up/down	VIEW 9	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3102/led	int	VIEW 10	0 or 1
/Mx/button/3102/led/color	color	VIEW 10	blue or red
/Mx/button/3102/led/blink	int	VIEW 10	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3102	up/down	VIEW 10	0 or 1

Update Address	Type	Name	Example
/Mx/button/3103/led	int	VIEW 11	0 or 1
/Mx/button/3103/led/color	color	VIEW 11	blue or red
/Mx/button/3103/led/blink	int	VIEW 11	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3103	up/down	VIEW 11	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3104/led	int	VIEW 12	0 or 1
/Mx/button/3104/led/color	color	VIEW 12	blue or red
/Mx/button/3104/led/blink	int	VIEW 12	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3104	up/down	VIEW 12	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3105/led	int	VIEW 13	0 or 1
/Mx/button/3105/led/color	color	VIEW 13	blue or red

/Mx/button/3105/led/blink	int	VIEW 13	0 or 1
Execute Address	Type	Name	Example
/Mx/button/3105	up/down	VIEW 13	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3106/led	int	VIEW 14	0 or 1
/Mx/button/3106/led/color	color	VIEW 14	blue or red
/Mx/button/3106/led/blink	int	VIEW 14	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3106	up/down	VIEW 14	0 or 1

Update Address	Туре	Name	Example
/Mx/button/3107/led	int	VIEW 15	0 or 1
/Mx/button/3107/led/color	color	VIEW 15	blue or red
/Mx/button/3107/led/blink	int	VIEW 15	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/3107	up/down	VIEW 15	0 or 1

Update Address	Type	Name	Example
/Mx/button/3108/led	int	VIEW 16	0 or 1
/Mx/button/3108/led/color	color	VIEW 16	blue or red
/Mx/button/3108/led/blink	int	VIEW 16	0 or 1
Execute Address	Type	Name	Example
/Mx/button/3108	up/down	VIEW 16	0 or 1

Keypad

Update Address	Туре	Name	Example
/Mx/button/2001/led	int	MACRO	0 or 1
/Mx/button/2001/led/color	color	MACRO	blue or red
/Mx/button/2001/led/blink	int	MACRO	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/2001	up/down	MACRO	0 or 1

Update Address	Type	Name	Example
/Mx/button/2002/led	int	PREVIEW	0 or 1
/Mx/button/2002/led/color	color	PREVIEW	blue or red
/Mx/button/2002/led/blink	int	PREVIEW	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/2002	up/down	PREVIEW	0 or 1

Update Address	Type	Name	Example
/Mx/button/2003/led	int	MENU	0 or 1
/Mx/button/2003/led/color	color	MENU	blue or red

/Mx/button/2003/led/blink	int	MENU	0 or 1
Execute Address	Type	Name	Example
/Mx/button/2003	up/down	MENU	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4321/led	int	FADE	0 or 1
/Mx/button/4321/led/color	color	FADE	blue or red
/Mx/button/4321/led/blink	int	FADE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4321	up/down	FADE	0 or 1

Update Address	Type	Name	Example
/Mx/button/4322/led	int	DELAY	0 or 1
/Mx/button/4322/led/color	color	DELAY	blue or red
/Mx/button/4322/led/blink	int	DELAY	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4322	up/down	DELAY	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4331/led	int	SNAPSHOT	0 or 1
/Mx/button/4331/led/color	color	SNAPSHOT	blue or red
/Mx/button/4331/led/blink	int	SNAPSHOT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4331	up/down	SNAPSHOT	0 or 1

Update Address	Туре	Name	Example
/Mx/button/4332/led	int	BANK	0 or 1
/Mx/button/4332/led/color	color	BANK	blue or red
/Mx/button/4332/led/blink	int	BANK	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/4332	up/down	BANK	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5101/led	int	EDIT	0 or 1
/Mx/button/5101/led/color	color	EDIT	blue or red
/Mx/button/5101/led/blink	int	EDIT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5101	up/down	EDIT	0 or 1

Update Address	Type	Name	Example
/Mx/button/5102/led	int	UNDO	0 or 1
/Mx/button/5102/led/color	color	UNDO	blue or red
/Mx/button/5102/led/blink	int	UNDO	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5102	up/down	UNDO	0 or 1

Update Address	Type	Name	Example
/Mx/button/5103/led	int	CLEAR	0 or 1
/Mx/button/5103/led/color	color	CLEAR	blue or red
/Mx/button/5103/led/blink	int	CLEAR	0 or 1
Execute Address	Type	Name	Example
/Mx/button/5103	up/down	CLEAR	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5104/led	int	COPY	0 or 1
/Mx/button/5104/led/color	color	COPY	blue or red
/Mx/button/5104/led/blink	int	COPY	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5104	up/down	COPY	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5106/led	int	MOVE	0 or 1
/Mx/button/5106/led/color	color	MOVE	blue or red
/Mx/button/5106/led/blink	int	MOVE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5106	up/down	MOVE	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5107/led	int	DELETE	0 or 1
/Mx/button/5107/led/color	color	DELETE	blue or red
/Mx/button/5107/led/blink	int	DELETE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5107	up/down	DELETE	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5401/led	int	RECORD	0 or 1
/Mx/button/5401/led/color	color	RECORD	blue or red
/Mx/button/5401/led/blink	int	RECORD	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5401	up/down	RECORD	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5402/led	int	UPDATE	0 or 1
/Mx/button/5402/led/color	color	UPDATE	blue or red
/Mx/button/5402/led/blink	int	UPDATE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5402	up/down	UPDATE	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5411/led	int	LOAD	0 or 1

/Mx/button/5411/led/color	color	LOAD	blue or red
/Mx/button/5411/led/blink	int	LOAD	0 or 1
Execute Address	Type	Name	Example

Update Address	Туре	Name	Example
/Mx/button/5412/led	int	GROUP	0 or 1
/Mx/button/5412/led/color	color	GROUP	blue or red
/Mx/button/5412/led/blink	int	GROUP	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5412	up/down	GROUP	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5413/led	int	CUE	0 or 1
/Mx/button/5413/led/color	color	CUE	blue or red
/Mx/button/5413/led/blink	int	CUE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5413	up/down	CUE	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5200	up/down	0	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5201	up/down	1	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5202	up/down	2	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5203	up/down	3	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5204	up/down	4	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5205	up/down	5	0 or 1

Execute Address	Type	Name	Example
/Mx/button/5206	up/down	6	0 or 1

Execute Address	Туре	Name	Example
/Mx/button/5207	up/down	7	0 or 1

Execute Address	Туре	Name	Example
/Mx/button/5208	up/down	8	0 or 1
<u>, , , , , , , , , , , , , , , , , , , </u>	1 1/		1
Execute Address	Туре	Name	Example
/Mx/button/5209	up/down	9	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5210	up/down	-	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5211	up/down	+	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5212	up/down		0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5213	up/down	Enter	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5214	up/down	/	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5215	up/down	Backspace	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5216	up/down	@	0 or 1
Execute Address	Туре	Name	Example
/N/N//hutton/E201	un /dauen	rII	0 0 1

/Mx/button/5301	up/down	Full	0 or 1

Execute Address	Туре	Name	Example
/Mx/button/5302	up/down	Through	0 or 1

Programmable Function-Keys

Update Address	Туре	Name	Example
/Mx/button/5601/led	int	F1	0 or 1
/Mx/button/5601/led/color	color	F1	blue or red
/Mx/button/5601/led/blink	int	F1	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5601	up/down	F1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/56A1/led	int	F2	0 or 1
/Mx/button/56A1/led/color	color	F2	blue or red
/Mx/button/56A1/led/blink	int	F2	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/56A1	up/down	F2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5602/led	int	F3	0 or 1
/Mx/button/5602/led/color	color	F3	blue or red
/Mx/button/5602/led/blink	int	F3	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5602	up/down	F3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/56A2/led	int	F4	0 or 1
/Mx/button/56A2/led/color	color	F4	blue or red
/Mx/button/56A2/led/blink	int	F4	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/56A2	up/down	F4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5603/led	int	F5	0 or 1
/Mx/button/5603/led/color	color	F5	blue or red
/Mx/button/5603/led/blink	int	F5	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/5603	up/down	F5	0 or 1

Update Address	Туре	Name	Example
/Mx/button/56A3/led	int	F6	0 or 1
/Mx/button/56A3/led/color	color	F6	blue or red
/Mx/button/56A3/led/blink	int	F6	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/56A3	up/down	F6	0 or 1

Update Address	Туре	Name	Example
/Mx/button/2101/led	int	F7	0 or 1
/Mx/button/2101/led/color	color	F7	blue or red
/Mx/button/2101/led/blink	int	F7	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/2101	up/down	F7	0 or 1

Update Address	Туре	Name	Example
/Mx/button/21A1/led	int	F8	0 or 1

/Mx/button/21A1/led/color	color	F8	blue or red
/Mx/button/21A1/led/blink	int	F8	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/21A1	up/down	F8	0 or 1

Update Address	Туре	Name	Example
/Mx/button/2102/led	int	F9	0 or 1
/Mx/button/2102/led/color	color	F9	blue or red
/Mx/button/2102/led/blink	int	F9	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/2102	up/down	F9	0 or 1

Update Address	Туре	Name	Example
/Mx/button/21A2/led	int	F10	0 or 1
/Mx/button/21A2/led/color	color	F10	blue or red
/Mx/button/21A2/led/blink	int	F10	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/21A2	up/down	F10	0 or 1

Update Address	Туре	Name	Example
/Mx/button/2103/led	int	F11	0 or 1
/Mx/button/2103/led/color	color	F11	blue or red
/Mx/button/2103/led/blink	int	F11	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/2103	up/down	F11	0 or 1

Update Address	Туре	Name	Example
/Mx/button/21A3/led	int	F12	0 or 1
/Mx/button/21A3/led/color	color	F12	blue or red
/Mx/button/21A3/led/blink	int	F12	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/21A3	up/down	F12	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5701/text	string	PF GROUP 1	<name></name>
/Mx/button/5701/color	color	PF GROUP 1	gray
/Mx/button/5701/text/color	color	PF GROUP 1	gray
Execute Address	Туре	Name	Example
/Mx/button/5701	up/down	PF GROUP 1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5702/text	string	PF GROUP 2	<name></name>
/Mx/button/5702/color	color	PF GROUP 2	gray
/Mx/button/5702/text/color	color	PF GROUP 2	gray
Execute Address	Туре	Name	Example

/Mx/button/5701	up/down	PF GROUP 2	0 or 1
-----------------	---------	------------	--------

Update Address	Туре	Name	Example
/Mx/button/5703/text	string	PF GROUP 3	<name></name>
/Mx/button/5703/color	color	PF GROUP 3	gray
/Mx/button/5703/text/color	color	PF GROUP 3	gray
Execute Address	Туре	Name	Example
/Mx/button/5703	up/down	PF GROUP 3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/5704/text	string	PF GROUP 4	<name></name>
/Mx/button/5704/color	color	PF GROUP 4	gray
/Mx/button/5704/text/color	color	PF GROUP 4	gray
Execute Address	Туре	Name	Example
/Mx/button/5704	up/down	PF GROUP 4	0 or 1

Update Address	Type	Name	Example
/Mx/button/5705/text	string	PF GROUP 5	<name></name>
/Mx/button/5705/color	color	PF GROUP 5	gray
/Mx/button/5705/text/color	color	PF GROUP 5	gray
Execute Address	Туре	Name	Example
/Mx/button/5705	up/down	PF GROUP 5	0 or 1

Execute Address	Туре	Name	Example
/Mx/scroll/5706/up	up/down	PF GROUP Scroll Up	0 or 1
/Mx/scroll/5706/down	up/down	PF GROUP Scroll Down	0 or 1

Programmer

Update Address	Туре	Name	Example
/Mx/button/6401/led	int	Last	0 or 1
/Mx/button/6401/led/color	color	Last	blue or red
/Mx/button/6401/led/blink	int	Last	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6401	up/down	Last	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6402/led	int	Next	0 or 1
/Mx/button/6402/led/color	color	Next	blue or red
/Mx/button/6402/led/blink	int	Next	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6402	up/down	Next	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6411/led	int	Swap Programmer	0 or 1
/Mx/button/6411/led/color	color	Swap Programmer	blue or red
/Mx/button/6411/led/blink	int	Swap Programmer	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6411	up/down	Swap Programmer	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6001/led	int	HIGHLIGHT	0 or 1
/Mx/button/6001/led/color	color	HIGHLIGHT	blue or red
/Mx/button/6001/led/blink	int	HIGHLIGHT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6001	up/down	HIGHLIGHT	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6003/led	int	CV	0 or 1
/Mx/button/6003/led/color	color	CV	blue or red
/Mx/button/6003/led/blink	int	CV	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6003	up/down	CV	0 or 1

Execute Address	Type	Name	Example
/Mx/button/6108	up/down	Link	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6101/text	string	BASE CHANNEL GROUP 1	<name></name>
/Mx/button/6101/color	color	BASE CHANNEL GROUP 1	gray
/Mx/button/6101/text/color	color	BASE CHANNEL GROUP 1	gray
Execute Address	Туре	Name	Example
/Mx/button/6101	up/down	BASE CHANNEL GROUP 1	0 or 1

Update Address	Type	Name	Example
/Mx/button/6102/text	string	BASE CHANNEL GROUP 2	<name></name>
/Mx/button/6102/color	color	BASE CHANNEL GROUP 2	gray
/Mx/button/6102/text/color	color	BASE CHANNEL GROUP 2	gray
Execute Address	Туре	Name	Example
/Mx/button/6102	up/down	BASE CHANNEL GROUP 2	0 or 1

Update Address	Type	Name	Example
/Mx/button/6103/text	string	BASE CHANNEL GROUP 3	<name></name>
/Mx/button/6103/color	color	BASE CHANNEL GROUP 3	gray
/Mx/button/6103/text/color	color	BASE CHANNEL GROUP 3	gray
Execute Address	Туре	Name	Example
/Mx/button/6103	up/down	BASE CHANNEL GROUP 3	0 or 1

Update Address	Type	Name	Example
/Mx/button/6104/text	string	BASE CHANNEL GROUP 4	<name></name>
/Mx/button/6104/color	color	BASE CHANNEL GROUP 4	gray
/Mx/button/6104/text/color	color	BASE CHANNEL GROUP 4	gray
Execute Address	Туре	Name	Example
/Mx/button/6104	up/down	BASE CHANNEL GROUP 4	0 or 1

Update Address	Type	Name	Example
/Mx/button/6105/text	string	BASE CHANNEL GROUP 5	<name></name>
/Mx/button/6105/color	color	BASE CHANNEL GROUP 5	gray
/Mx/button/6105/text/color	color	BASE CHANNEL GROUP 5	gray
Execute Address	Type	Name	Example
/Mx/button/6105	up/down	BASE CHANNEL GROUP 5	0 or 1

Update Address	Type	Name	Example
/Mx/button/6201/text	string	EFFECT CHANNEL GROUP 1	<name></name>
/Mx/button/6201/color	color	EFFECT CHANNEL GROUP 1	gray
/Mx/button/6201/text/color	color	EFFECT CHANNEL GROUP 1	gray
Execute Address	Туре	Name	Example
/Mx/button/6201	up/down	EFFECT CHANNEL GROUP 1	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6202/text	string	EFFECT CHANNEL GROUP 2	<name></name>
/Mx/button/6202/color	color	EFFECT CHANNEL GROUP 2	gray
/Mx/button/6202/text/color	color	EFFECT CHANNEL GROUP 2	gray
Execute Address	Туре	Name	Example
/Mx/button/6202	up/down	EFFECT CHANNEL GROUP 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6203/text	string	EFFECT CHANNEL GROUP 3	<name></name>
/Mx/button/6203/color	color	EFFECT CHANNEL GROUP 3	gray
/Mx/button/6203/text/color	color	EFFECT CHANNEL GROUP 3	gray
Execute Address	Туре	Name	Example
/Mx/button/6203	up/down	EFFECT CHANNEL GROUP 3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6204/text	string	EFFECT CHANNEL GROUP 4	<name></name>
/Mx/button/6204/color	color	EFFECT CHANNEL GROUP 4	gray
/Mx/button/6204/text/color	color	EFFECT CHANNEL GROUP 4	gray
Execute Address	Туре	Name	Example
/Mx/button/6204	up/down	EFFECT CHANNEL GROUP 4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6205/text	string	EFFECT CHANNEL GROUP 5	<name></name>
/Mx/button/6205/color	color	EFFECT CHANNEL GROUP 5	gray

/Mx/button/6205/text/color	color	EFFECT CHANNEL GROUP 5	gray
Execute Address	Type	Name	Example
/Mx/button/6205	up/down	EFFECT CHANNEL GROUP 5	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6111/led	int	BASE CHANNEL 1	0 or 1
/Mx/button/6111/led/color	color	BASE CHANNEL 1	blue or red
/Mx/button/6111/led/blink	int	BASE CHANNEL 1	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6111	up/down	BASE CHANNEL 1	0 or 1

Update Address	Type	Name	Example
/Mx/button/6121/led	int	BASE CHANNEL 2	0 or 1
/Mx/button/6121/led/color	color	BASE CHANNEL 2	blue or red
/Mx/button/6121/led/blink	int	BASE CHANNEL 2	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6121	up/down	BASE CHANNEL 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6131/led	int	BASE CHANNEL 3	0 or 1
/Mx/button/6131/led/color	color	BASE CHANNEL 3	blue or red
/Mx/button/6131/led/blink	int	BASE CHANNEL 3	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6131	up/down	BASE CHANNEL 3	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6141/led	int	BASE CHANNEL 4	0 or 1
/Mx/button/6141/led/color	color	BASE CHANNEL 4	blue or red
/Mx/button/6141/led/blink	int	BASE CHANNEL 4	0 or 1
Execute Address	Type	Name	Example
/Mx/button/6141	up/down	BASE CHANNEL 4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6211/led	int	EFFECT CHANNEL 1	0 or 1
/Mx/button/6211/led/color	color	EFFECT CHANNEL 1	blue or red
/Mx/button/6211/led/blink	int	EFFECT CHANNEL 1	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6211	up/down	EFFECT CHANNEL 1	0 or 1

Update Address	Type	Name	Example
/Mx/button/6221/led	int	EFFECT CHANNEL 2	0 or 1
/Mx/button/6221/led/color	color	EFFECT CHANNEL 2	blue or red
/Mx/button/6221/led/blink	int	EFFECT CHANNEL 2	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6221	up/down	EFFECT CHANNEL 2	0 or 1

Update Address	Туре	Name	Example
/Mx/button/6231/led	int	EFFECT CHANNEL 3	0 or 1
/Mx/button/6231/led/color	color	EFFECT CHANNEL 3	blue or red
/Mx/button/6231/led/blink	int	EFFECT CHANNEL 3	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6231	up/down	EFFECT CHANNEL 3	0 or 1

Update Address	Type	Name	Example
/Mx/button/6241/led	int	EFFECT CHANNEL 4	0 or 1
/Mx/button/6241/led/color	color	EFFECT CHANNEL 4	blue or red
/Mx/button/6241/led/blink	int	EFFECT CHANNEL 4	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/6241	up/down	EFFECT CHANNEL 4	0 or 1

Update Address	Туре	Name	Example
/Mx/belt/6112/channelName	string	VALUE BASE 1	<name></name>
/Mx/belt/6112/channelValue	string	VALUE BASE 1	<value></value>
/Mx/belt/6112/color	color	VALUE BASE 1	gray
/Mx/belt/6112/channelValue/color	color	VALUE BASE 1	gray
/Mx/belt/6112/channelName/color	color	VALUE BASE 1	gray
Execute Address	Type	Name	Example
/Mx/belt/6112/	up/down	VALUE BASE 1	0 or 1

Update Address	Type	Name	Example
/Mx/belt/6122/channelName	string	VALUE BASE 2	<name></name>
/Mx/belt/6122/channelValue	string	VALUE BASE 2	<value></value>
/Mx/belt/6122/color	color	VALUE BASE 2	gray
/Mx/belt/6122/channelValue/color	color	VALUE BASE 2	gray
/Mx/belt/6122/channelName/color	color	VALUE BASE 2	gray
Execute Address	Type	Name	Example
/Mx/belt/6122/	up/down	VALUE BASE 2	0 or 1

Update Address	Туре	Name	Example
/Mx/belt/6132/channelName	string	VALUE BASE 3	<name></name>
/Mx/belt/6132/channelValue	string	VALUE BASE 3	<value></value>
/Mx/belt/6132/color	color	VALUE BASE 3	gray
/Mx/belt/6132/channelValue/color	color	VALUE BASE 3	gray
/Mx/belt/6132/channelName/color	color	VALUE BASE 3	gray
Execute Address	Type	Name	Example
/Mx/belt/6132/	up/down	VALUE BASE 3	0 or 1

Update Address	Туре	Name	Example
/Mx/belt/6142/channelName	string	VALUE BASE 4	<name></name>
/Mx/belt/6142/channelValue	string	VALUE BASE 4	<value></value>
/Mx/belt/6142/color	color	VALUE BASE 4	gray
/Mx/belt/6142/channelValue/color	color	VALUE BASE 4	gray

/Mx/belt/6142/channelName/color	color	VALUE BASE 4	gray
Execute Address	Type	Name	Example
/Mx/belt/6142/	up/down	VALUE BASE 4	0 or 1

Update Address	Туре	Name	Example
/Mx/belt/6212/channelName	string	VALUE EFFECT 1	<name></name>
/Mx/belt/6212/channelValue	string	VALUE EFFECT 1	<value></value>
/Mx/belt/6212/color	color	VALUE EFFECT 1	gray
/Mx/belt/6212/channelValue/color	color	VALUE EFFECT 1	gray
/Mx/belt/6212/channelName/color	color	VALUE EFFECT 1	gray
Execute Address	Type	Name	Example
/Mx/belt/6212/	up/down	VALUE EFFECT 1	0 or 1

Update Address	Type	Name	Example
/Mx/belt/6222/channelName	string	VALUE EFFECT 2	<name></name>
/Mx/belt/6222/channelValue	string	VALUE EFFECT 2	<value></value>
/Mx/belt/6222/color	color	VALUE EFFECT 2	gray
/Mx/belt/6222/channelValue/color	color	VALUE EFFECT 2	gray
/Mx/belt/6222/channelName/color	color	VALUE EFFECT 2	gray
Execute Address	Type	Name	Example
/Mx/belt/6222/	up/down	VALUE EFFECT 2	0 or 1

Update Address	Type	Name	Example
/Mx/belt/6232/channelName	string	VALUE EFFECT 3	<name></name>
/Mx/belt/6232/channelValue	string	VALUE EFFECT 3	<value></value>
/Mx/belt/6232/color	color	VALUE EFFECT 3	gray
/Mx/belt/6232/channelValue/color	color	VALUE EFFECT 3	gray
/Mx/belt/6232/channelName/color	color	VALUE EFFECT 3	gray
Execute Address	Type	Name	Example
/Mx/belt/6232/	up/down	VALUE EFFECT 3	0 or 1

Update Address	Type	Name	Example
/Mx/belt/6242/channelName	string	VALUE EFFECT 4	<name></name>
/Mx/belt/6242/channelValue	string	VALUE EFFECT 4	<value></value>
/Mx/belt/6242/color	color	VALUE EFFECT 4	gray
/Mx/belt/6242/channelValue/color	color	VALUE EFFECT 4	gray
/Mx/belt/6242/channelName/color	color	VALUE EFFECT 4	gray
Execute Address	Type	Name	Example
/Mx/belt/6242/	up/down	VALUE EFFECT 4	0 or 1

Update Address	Туре	Name	Example
/Mx/button/7001/led	int	TRACKFUNC P/T	0 or 1
/Mx/button/7001/led/color	color	TRACKFUNC P/T	blue or red
/Mx/button/7001/led/blink	int	TRACKFUNC P/T	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7001	up/down	TRACKFUNC P/T	0 or 1

Update Address	Туре	Name	Example
/Mx/button/7004/led	int	MODE	0 or 1
/Mx/button/7004/led/color	color	MODE	blue or red
/Mx/button/7004/led/blink	int	MODE	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7004	up/down	MODE	0 or 1

Update Address	Туре	Name	Example
/Mx/button/7301/led	int	NAVIGATE UP	0 or 1
/Mx/button/7301/led/color	color	NAVIGATE UP	blue or red
/Mx/button/7301/led/blink	int	NAVIGATE UP	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7301	up/down	NAVIGATE UP	0 or 1

Update Address	Туре	Name	Example
/Mx/button/7302/led	int	NAVIGATE LEFT	0 or 1
/Mx/button/7302/led/color	color	NAVIGATE LEFT	blue or red
/Mx/button/7302/led/blink	int	NAVIGATE LEFT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7302	up/down	NAVIGATE LEFT	0 or 1

Update Address	Туре	Name	Example
/Mx/button/7303/led	int	NAVIGATE DOWN	0 or 1
/Mx/button/7303/led/color	color	NAVIGATE DOWN	blue or red
/Mx/button/7303/led/blink	int	NAVIGATE DOWN	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7303	up/down	NAVIGATE DOWN	0 or 1

Update Address	Type	Name	Example
/Mx/button/7304/led	int	NAVIGATE RIGHT	0 or 1
/Mx/button/7304/led/color	color	NAVIGATE RIGHT	blue or red
/Mx/button/7304/led/blink	int	NAVIGATE RIGHT	0 or 1
Execute Address	Туре	Name	Example
/Mx/button/7304	up/down	NAVIGATE RIGHT	0 or 1

Configuration

Update Address	Туре	Name	Example
/Mx/configuration/deviceSpace	string	Device Space ID Number	<id></id>
Execute Address	Туре	Name	Example
/Mx/configuration/deviceSpace/down	up/down	Device Space ID Number	0 or 1
/Mx/configuration/deviceSpace/up	up/down	Device Space ID Number	0 or 1